

# Alias Email

## Question

Is there a way to have alias email instead of multiple email account? Like auto-forwarding email to the main email without creating other email accounts? And email accounts from a different domain? We're running the standalone version.

## Answer

Standalone only.

Create **/home/crossbox/app/config/exim/virtual\_domains** file that contains a list of domains you want to forward **from**:

```
domain-one.com
domain-two.net
domain-three.org
```

Next, go to **/home/crossbox/app/config/exim/virtual** and for each domain create a separate file with the domain name as file name, for example:

```
/home/crossbox/app/config/exim/virtual/domain-one.com
/home/crossbox/app/config/exim/virtual/domain-two.net
/home/crossbox/app/config/exim/virtual/domain-three.org
```

Within those files, define from what e-mail address(es) you want to forward and to where. For example:

```
* : *@domain-four.com
```

The example above will forward all e-mail sent to \*@domain-one.com, \*@domain-two.net, \*@domain-three.org, to the **same e-mail address** at @domain-four.com

Instead of using a wildcard to match any email address, you can also be more specific like:

```
* : email@domain-four.com
```

When you're done, you'll need to run:

```
crossbox config reload && crossbox restart exim
```

- 
- Revision #5
  - Created 5 years ago by [Docs Admin](#)
  - Updated 2 years ago by [Docs Admin](#)